

Transcripts and support reports

OpenGlasses · a guide for support · September 2026

What's new

1. **Transcripts.** Save everything said on a job, or on every job in a day, as a text file.
2. **Support reports.** A transcript with extra detail for troubleshooting: which AI answered, how long it took, which manual pages it used, and whether anything went wrong. Passwords and keys are hidden automatically.
3. **Send to support after a problem.** When the assistant fails to answer, the app offers to send a report.

Nothing is ever sent on its own. The person always sees the report first and taps Send.

Where to find it

To do this	Go here
Save one job's transcript	Job tab → tap a past job → Export transcript... → Transcript
Send one job to support	Job tab → tap a past job → Export transcript... → Support report with troubleshooting details
Save or send a whole day	Job tab → Past jobs → Export a day... → pick a day → Transcript or Support report
Send today to support, from anywhere	Settings → Diagnostics & Support → Send Today's Activity
Send straight after a problem	tap Send to support on the That didn't work banner

The review screen

Every support report opens on a review screen first. It shows:

- how many jobs and conversations are in the report, and how many times the assistant failed;
- anything that was hidden, such as a password;
- the report itself, to scroll through.

Two buttons send it:

- **Email to Support** opens an email to support with the report attached. You can add a note before sending.
- **Share the File...** sends it another way, such as Messages or AirDrop.

For a whole day, a switch lets you include or leave out conversations that weren't part of a job.

When something goes wrong

If the assistant can't answer, a banner appears at the top of the screen:

That didn't work — 10:42 — no internet connection. **Send to support**

Tap **Send to support** to open the review screen for that day. Tap **x** to dismiss it; it won't appear again for 10 minutes.

Reading a report

Each job starts with its job number, the machine, and when it started and finished. Then everything that happened, in time order:

```
09:13 Technician: How do I check the flame sensor?
09:13 · AI turn answered
      manual pages: Lennox SLP99 manual, page 12
      timing: reply complete after 3.4 s
09:14 Assistant: Turn the power off, then remove the sensor ...
09:30 · AI turn FAILED – offline
```

- **Technician** and **Assistant** lines are the conversation.
- **AI turn** lines show what happened behind the scenes for the line above: which AI answered, which manual pages it used, whether a photo was sent, and how long it took. **FAILED** marks a problem.
- At the end there are details about the phone and glasses, for the support team.

What a report doesn't include

- **Recordings.** The app never keeps audio, only the written transcript.
- **The live conversation modes** (Gemini Live and OpenAI Realtime). These don't save conversations yet, so use the normal voice mode for the pilot.

Privacy

The app keeps a record of each AI request for 14 days, on the phone only. It contains no conversation, just timings, pages used and errors. It can be deleted in **Settings** → **Diagnostics & Support** → **Delete AI Turn Records**. A support report does contain conversations, so it is only made when someone asks for one, and only sent when they send it.

Quick test (1 minute)

You need one finished job on the phone, and Mail set up with an email account.

Send a job's transcript

1. **Job** tab → tap a past job → **Export transcript...** → **Support report with troubleshooting details**.
2. Tap **Email to Support**, then **Send**.

Send it at the end of the day

1. **Settings** → **Diagnostics & Support** → **Send Today's Activity**.
2. Tap **Email to Support**, then **Send**.

Send it when there's a problem

1. Turn on **Airplane Mode** and ask the assistant a question.
2. When the **That didn't work** banner appears, tap **Send to support**.
3. Turn **Airplane Mode** off, tap **Email to Support**, then **Send**.

If any step doesn't work, send **Today's Activity** and say in the email which step it was.